

HOW TO... Check Your Chicks Are Comfortable

WHY IS CHICK COMFORT IMPORTANT?

- When chicks hatch they are not able to control their body temperature.
- The correct holding temperature for chicks will depend on air speed and humidity.
- If chicks are too hot or cold they will be stressed, use more energy and, if too hot, will pant and lose water at a faster rate.
- Chicks that are not at the correct temperature will have poorer broiler performance.





07



HOW TO MEASURE CHICK COMFORT?

- Chick comfort can be determined by measuring chick vent temperature using a medical ear thermometer.
- Chick vent temperature is highly correlated with deep body temperature, although it tends to be 0.6°C (1°F) cooler.
- The optimum chick vent temperature is 39.4 – 40.5°C (103 – 105°F).



• Monitor chick behavior; chicks use behavior to help control their body temperature.

box.

Chicks that are too cold, below 39.4°C (103°F), start to huddle and have cold legs and feet.



Chicks at correct temperature are quiet and evenly spread out in the



Chicks that are too hot, above 40.5°C (105°F), start panting.





HOW TO ..

Check Your Chicks Are Comfortable

HOW TO ..

Check Your Chicks Are Comfortable

07

WHEN AND WHERE TO MEASURE CHICK VENT TEMPERATURE

- Chick vent temperature should be used to check chick comfort in hatchers, chick rooms, chick trucks and during the first 2 days of brooding.
- Chicks should be sampled throughout the area where they are being held and from near the top, middle and bottom of chick box stacks.
- Pay particular attention to areas:
 - where chicks are observed to be panting or huddling
 - where there is fast air movement around the chick boxes
 - near walls and doors











Check Your Chicks Are Comfortable

07

HOW TO.

PROCEDURE TO MEASURE CHICK VENT TEMPERATURE

- Equipment required: Medical infrared ear thermometer recommended brand Braun ThermoScan[®] IRT4520 thermometer.
- Other brands and models are available but they may not be as accurate.



Step 1:

Check that the measuring tip of the thermometer is clean and has a new plastic cover on.

Step 2:

If, to take a measurement, the chicks need to be removed from the environment where they are being held (e.g. when checking in hatchers), the measurements need to be made within 10 minutes of the chicks being removed.

Step 3:

At each sampling position measure the vent temperature of 5 chicks. Reject any chicks with wet or dirty vents.

Note: If chicks are huddling do not select chicks from the center of the huddle.

Step 4:

Pick up one chick, and hold it so that you can see the vent. With your thumb, gently push the rump of the chick upwards, so that the vent is exposed.

Step 5:

Put the tip of the ThermoScan[®] gently onto the vent, making sure it only touches bare skin, and press the button. Wait for the light to stop flashing, and note the temperature on a recording sheet.









PROCEDURE TO MEASURE CHICK VENT TEMPERATURE

Example of a recording sheet: Target Chick Vent Temperature 39.4 – 40.5°C (103 - 105°F)

Stack	Box in	Chick Number						
Location	Stack	1	2	3	4	5	Mean	Comment
Front Right	Тор	39.4°C (102.9°F)	39.6°C (103.3°F)	39.3°C (102.7°F)	39.5 °C (103.1°F)	39.8°C (103.6°F)	39.5°C (103.1°F)	Okay
	Middle	40.2°C (104.4°F)	39.8°C (103.6° F)	40.0°C (104.0°F)	40.1°C (104.2°F)	40.1°C (104.2°F)	40.0°C (104.0°F)	
	Bottom	39.5°C (103.1°F)	39.2°C (102.6°F)	39.9°C (103.8°F)	39.7°C (103.5°F)	39.4°C (102.9°F)	39.5°C (103.1°F)	
Front Left	Тор	39.8°C (103.6°F)	39.6°C (103.3° F)	39.7°C (103.5°F)	40.0°C (104.0°F)	39.7°C (103.5°F)	39.8°C (103.6°F)	Okay
	Middle	40.6°C (105.1°F)	40.5°C (104.9°∓)	40.3°C (104.5°F)	40.4°C (104.7°F)	40.4°C (104.7°F)	40.4℃ (104.7°F)	
	Bottom	39.5°C (103.1°F)	39.8°C (103.6°F)	39.7°C (103.5°F)	39.5°C (103.1°F)	39.4°C (102.9°F)	39.6°C (103.3°F)	
Back Right	Тор	38.3°C (100.9°F)	38.5°C (101.3°F)	38.6°C (101.5°F)	38.FC (101.FF)	39.4°C (102.9°F)	38.FC (101.FF)	Chícks huddlíng - Cold draft from door
	Middle	38.8°C (101.8°F)	38.6°C (101.5°F)	39.4°C (102.9°F)	39.3°C (102.7°F)	38.8°C (101.8°F)	39.0°C (102.2°F)	
	Bottom	38.5°C (101.3°F)	38.2°C (100.8°F)	38.2°C (100.8°F)	38.4°C (101.1°F)	38.2°C (100.8°F)	38.3°C (100.9°F)	
Back Left	Тор	40.5°C (104.9°F)	40.4°C (104.7°F)	40.6°C (105.1°F)	40.5°C (104.9°F)	40.3°C (104.5°F)	40.4°C (104.7°F)	Chícks pantíng - not enough space between stacks
	Middle	41.0°C (105.8° F)	40.8°C (105.4°F)	41.3°C (106.3°F)	41.2°C (106.2°F)	41.0°C (105.8° F)	41.1°C (106.0° F)	
	Bottom	40.9°C (105.6°F)	40.8°C (105.4°F)	40.8°C (105.4°F)	41.0°C (105.8° F)	40.9°C (105.6°F)	40.9°C (105.6°F)	

HOW TO... Check Your Chicks Are Comfortable

HOW TO... Check Your Chicks Are Comfortable

INTERPRETATION OF RESULTS

07

	Vent Temperature less than 39.4°C (103°F)	Vent Temperature more than 40.5°C (105°F)
All chicks	Increase holding temperature	Decrease holding temperature
Some chicks	 Cold air drafts Wet floors Wet chicks (e.g. after vaccination) Uneven air circulation around boxes Chicks held too long on carousels 	 Poor air circulation around chick boxes Chick boxes: too close together too close to a wall too near heater units

MORE INFORMATION

- Ross Tech Investigating Hatchery Practice
- AVIATECH Hatchery Maintenance
- Others in the Hatchery How To series:
 - 01 Measure Egg Water Loss
 - 02 Measure Chick Yield
 - 03 Measure Eggshell Temperature
 - 04 Identify Infertile Eggs & Early Deads
 - 05 Break Out and Analyze Hatch Debris
 - 06 Monitor Setter Temperature Variation

